

DEFINE ATTRIBUTE CHANGE SPECIFICATIONS

SpoolOrganizer can change certain spool file attributes as it processes a spool entry. For example a spool entry can be held as it is moved to an outq. The administrator can create multiple Attribute Change descriptions, and refer to the specific one. For example the Monitor description, Selection Criteria description, and Bundle Entry description definition screens can refer to an Attribute Change description.

Warning: SpoolOrganizer does not check the validity of user-changed attributes. It only performs minor syntax checking. Many attributes are valid or invalid depending on other attributes, or the type of printer the spool entry is printed on. It is the Administrator's responsibility to test all attribute changes for validity.

Broderick Data Systems may consider any technical support call that is traced to invalid user changes of spool entry attributes as a chargeable call.

Press **F6** to add an Attribute Change Description and enter a name. The following screen will appear:

Spool Organizer/400			4/03/96	
Define Attribute Change Specifications			15:17:18	
Name: _____				
Qualifying			Change	
Field	Rel	Value	Field	Value
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
Text: _____				
F3=Exit F12=Cancel Current Operation				

The above parameters have the following definitions:

Qualifying Expression

Specifies a test to perform to determine if the change is to be performed. Specify a field, relation, and value. The expression is compared to the spool entry attribute. If true, the change expression is performed.

SPOOLORGANIZER/400™

Field

Specifies the spool entry attribute. Specify one of the valid fields listed below.

Rel: (Relation)

Specify one of the following:

EQ	Equal to
NE	Not equal to
GT	Greater than
LT	Less than
GE	Greater than or equal to
LE	Less than or Equal to

Value

Specify the spool attribute value to compare.

Note: Specify a blank field, relation, and value to indicate the change is to be performed unconditionally.

Change Expression

Specifies the Attribute and the new value to substitute. Specify a field and value.

Field

Specifies the spool entry attribute. Specify one of the valid fields listed below.

Value

Specify the new spool attribute value.

Valid Fields

Below is a list of valid spool attributes that can be tested/changed. Most attributes correspond to **OS/400** attribute names. See the **OS/400 CRTPRTF** command for a description. Attributes that have special meanings are described below.

ALIGN	FILESEP	HOLD	LPI	PRTQLTY	UOM
COPIES	FOLD	JOBNAME	MULTIUP	RPLUNPRT	USRDTA
CPI	FONT	JONBUM	OUTPTY	SAVE	
DRAWER	FORMFEED	JOBUSER	OVFLW	SCHEDULE	
DUPLEX	FORMTYPE	JUSTIFY	PAGRTT	SPLFILE	

BAOVL	Back overlay name
BAOVLLIB	Back overlay library
BAOVLOFFDN	Back overlay offset down
BAOVLOFFAC	Back overlay offset across
FONTPOINT	Font point size
FROVL	Front overlay name
FROVLLIB	Front overlay library

DEFINE ATTRIBUTE CHANGE SPECIFICATIONS

FROVLOFFDN	Front overlay offset down
FROVLOFFAC	Front overlay offset across
MONITOR	The SpoolOrg Monitor name (Qualifying field only)
PAGEEND	Page range ending page
PAGELEN	Page Length (lines per page)
PAGESTART	Page range starting page
PAGEWIDTH	Page Width (characters per line)
RPLCHAR	replace unprintables replacement character

Note: Changes to the Job Name and Job User attributes are ignored by Outq Distribution List entries.